
MMM MMM TTTTTTTTTTTTTTT HHH HHH RRRRRRRRRRR TTTTTTTTTTTTTTT LLL
MMMMMM MMMMMM TTT HHH HHH RRR RRR TTT LLL
MMM MMM MMM TTT HHH HHH RRR RRR TTT LLL
MMM MMM MMM TTT HHHHHHHHHHHHHHH RRRRRRRRRRR TTT LLL
MMM MMM MMM TTT HHH HHH RRR RRR TTT LLL
MMM MMM MMM TTT HHH HHH RRR RRR TTT LLL
MMM MMM MMM TTT HHH HHH RRR RRR TTT LLLLLLLLLLLLLLL

```
MM      MM  TTTTTTTTTT  HH      HH    AAAAAA    MM      MM    OOOOOO    DDDDDDDD
MM      MM  TTTTTTTTTT  HH      HH    AAAAAA    MM      MM    OOOOOO    DDDDDDDD
MMMM  MMMM      TT      HH      HH   AA    AA   MMMM  MMMM   OO    OO  DD      DD
MMMM  MMMM      TT      HH      HH   AA    AA   MMMM  MMMM   OO    OO  DD      DD
MM  MM  MM      TT      HH      HH   AA    AA   MM  MM  MM   OO    OO  DD      DD
MM  MM  MM      TT      HH      HH   AA    AA   MM  MM  MM   OO    OO  DD      DD
MM      MM      TT      HHHHHHHHHH   AA    AA   MM      MM   OO    OO  DD      DD
MM      MM      TT      HHHHHHHHHH   AA    AA   MM      MM   OO    OO  DD      DD
MM      MM      TT      HH      HH   AAAAAAAAAA   MM      MM   OO    OO  DD      DD
MM      MM      TT      HH      HH   AAAAAAAAAA   MM      MM   OO    OO  DD      DD
MM      MM      TT      HH      HH   AA    AA   MM      MM   OO    OO  DD      DD
MM      MM      TT      HH      HH   AA    AA   MM      MM   OO    OO  DD      DD
MM      MM      TT      HH      HH   AA    AA   MM      MM    OOOOOO   DDDDDDDD
MM      MM      TT      HH      HH   AA    AA   MM      MM    OOOOOO   DDDDDDDD

LL              IIIIII      SSSSSSSS
LL              IIIIII      SSSSSSSS
LL                II      SS
LL                II      SS
LL                II      SS
LL                II      SS
LL                II        SSSSSS
LL                II        SSSSSS
LL                II              SS
LL                II              SS
LL                II              SS
LL                II              SS
LLLLLLLLLL      IIIIII    SSSSSSSS
LLLLLLLLLL      IIIIII    SSSSSSSS
```

Table of contents

```
0000     1          .TITLE  MTH$AMOD
0000     2          .IDENT  /3-001/                 ; File: MTHAMOD.MAR Edit: JCW3001
0000     3
0000     4 ;
0000     5 ;*****************************************************************************
0000     6 ;*                                                                           *
0000     7 ;*  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY                                  *
0000     8 ;*  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.                   *
0000     9 ;*  ALL RIGHTS RESERVED.                                                     *
0000    10 ;*                                                                           *
0000    11 ;*  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED    *
0000    12 ;*  ONLY IN  ACCORDANCE WITH  THE  TERMS  OF  SUCH  LICENSE  AND WITH THE   *
0000    13 ;*  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR  ANY  OTHER    *
0000    14 ;*  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY    *
0000    15 ;*  OTHER PERSON.  NO TITLE TO AND OWNERSHIP OF  THE  SOFTWARE IS  HEREBY    *
0000    16 ;*  TRANSFERRED.                                                             *
0000    17 ;*                                                                           *
0000    18 ;*  THE INFORMATION IN THIS SOFTWARE IS  SUBJECT TO CHANGE WITHOUT NOTICE    *
0000    19 ;*  AND  SHOULD  NOT  BE  CONSTRUED AS  A COMMITMENT BY DIGITAL EQUIPMENT   *
0000    20 ;*  CORPORATION.                                                             *
0000    21 ;*                                                                           *
0000    22 ;*  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE  OR  RELIABILITY OF ITS    *
0000    23 ;*  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.                  *
0000    24 ;*                                                                           *
0000    25 ;*                                                                           *
0000    26 ;*****************************************************************************
0000    27 ;
0000    28
0000    29 ;++
0000    30 ; FACILITY: MATH LIBRARY
0000    31 ;
0000    32 ; ABSTRACT:
0000    33 ;
0000    34 ;       This module contains the routine MTH$AMOD:
0000    35 ;       It returns the remainder of the division of arg1/arg2 using
0000    36 ;       the following equation:
0000    37 ;               arg1 - (int(arg1/arg2))*arg2
0000    38 ;
0000    39 ;
0000    40 ;--
0000    41 ;
0000    42 ; AUTHOR: Bob Hanek, CREATION DATE: 21-DEC-1982
0000    43 ;
0000    44 ; MODIFIED BY:
0000    45 ;         Jeffrey C. Wiener, 29-DEC-82
0000    46 ;
0000    47 ;--
0000    48
0000    49          .SBTTL  HISTORY  ;  Detailed Current Edit History
0000    50 ;
0000    51 ; Edit History for Version 3.0:
0000    52 ;
0000    53 ; 3-001 Original version of a complete rewrite          JCW  29-DEC-82
0000    54 ;
```

```
                        .SBTTL  DECLARATIONS
                ;
                ; INCLUDE FILES:
                ;
                ;       NONE
                ;
                ; EXTERNAL SYMBOLS:
                ;
                        .DSABL  GBL             ; Force all external symbols to be declared
                        .EXTRN  MTH$$SIGNAL
                        .EXTRN  MTH$K_FLOUNDMAT
                        .EXTRN  MTH$K_INVARGMAT
                ;
                ; LIBRARY MACROS CALLS:
                ;
                        $SFDEF                          ; Define SF$ (stack frame) symbols
                ;
                ; EQUATED SYMBOLS:
                ;
                ;       NONE
                ;
                ; OWN STORAGE:
                ;
                ;       NONE
                ;
                ; PSECT DECLARATIONS:
                ;
00000000        .PSECT  _MTH$CODE               PIC, SHR, LONG, EXE, NOWRT
                ;
                ; CONSTANTS:
                ;
                ;       NONE
                ;
```

```
                     0000     90          .SBTTL  MTH$AMOD - F REAL*4 remainder
                     0000     91 ;++
                     0000     92 ; FUNCTIONAL DESCRIPTION:
                     0000     93 ;
                     0000     94 ;       Return the remainder of arg1/arg2 in F_floating point format
                     0000     95 ;       Remainder = arg1 - (int(arg1/arg2))*arg2
                     0000     96 ;
                     0000     97 ; The algorithm used to evaluate the AMOD function is as follows:
                     0000     98 ;
                     0000     99 ;                   X = the first argument.
                     0000    100 ;                   Y = the second argument.
                     0000    101 ;       step 1. m = the exponent of Y.
                     0000    102 ;                   n = the exponent of X.
                     0000    103 ;                   c = n - m
                     0000    104 ;                   If c < 0, end with result = X.
                     0000    105 ;       step 2. I = the fractional part of X*2^24
                     0000    106 ;                   J = the fractional part of Y*2^24
                     0000    107 ;                   If I >= J, I = I - J
                     0000    108 ;       step 3. c = c - 31
                     0000    109 ;                   If c < 0 go to step 7.
                     0000    110 ;       step 4. L = 2^31*I
                     0000    111 ;                   I = L - J*int(L/J)
                     0000    112 ;                   c = c - 31
                     0000    113 ;                   If c >= 0 go to step 4.
                     0000    114 ;       step 5. c = c + 31
                     0000    115 ;                   If c >= 0 go to step 7.
                     0000    116 ;       step 6. L = 2^c*I
                     0000    117 ;                   I = L - J*int(L/J)
                     0000    118 ;       step 7. Result = 2^(m-24) * I
                     0000    119 ;
                     0000    120 ; CALLING SEQUENCE:
                     0000    121 ;
                     0000    122 ;       Remainder.wf.v = MTH$AMOD (dividend.rf.r, divisor.rf.r)
                     0000    123 ;
                     0000    124 ; INPUT PARAMETERS:
                     0000    125 ;
                     0000    126 ;       The two input parameters are F_floating-point values. They are
                     0000    127 ;       passed by reference.
                     0000    128 ;
00000004             0000    129         DIVIDEND = 4                            ; Dividend = X in the algorithm.
00000008             0000    130         DIVISOR  = 8                            ; Divisor  = Y in the algorithm.
                     0000    131 ;
                     0000    132 ; IMPLICIT INPUTS:
                     0000    133 ;
                     0000    134 ;       NONE
                     0000    135 ;
                     0000    136 ; FUNCTION VALUE:
                     0000    137 ;
                     0000    138 ;       Remainder of the division of arg1/arg2 is returned as an
                     0000    139 ;       F_floating point value.
                     0000    140 ;
                     0000    141 ; IMPLICIT OUTPUTS:
                     0000    142 ;
                     0000    143 ;       NONE
                     0000    144 ;
                     0000    145 ; COMPLETION CODES:
                     0000    146 ;
```

```
                                0000   147 ;       NONE
                                0000   148 ;
                                0000   149 ; SIDE EFFECTS:
                                0000   150 ;
                                0000   151 ;       MTH$_INVARGMAT - Invalid argument to math library if the divisor is zero.
                                0000   152 ;       MTH$_FLOUNDMAT - Floating underflow in math library is signaled if
                                0000   153 ;          the FU bit is set in the callers PSL.
                                0000   154 ;
                                0000   155 ;--
                                0000   156
                        001C    0000   157          .ENTRY MTH$AMOD,        ^M<R2, R3, R4>
                                0002   158
              52    08 BC       50    0002   159          MOVF    @DIVISOR(AP), R2                ; R2 = Y, the divisor
            52    8000 8F       AA    0006   160          BICW2   #^X8000, R2                     ; R2 = |Y|
                        10        12    000B   161          BNEQ    START                           ; |Y| <> 0
            50    01    0F        78    000D   162          ASHL    #15, #1, R0                     ; |Y|=0. Division by zero case
              7E    00'8F         9A    0011   163          MOVZBL  #MTH$K_INVARGMAT, -(SP)         ; error code
      00000000'GF    01           FB    0015   164          CALLS   #1, G^MTH$$SIGNAL               ; signal the error
                     04           001C   165          RET
                                001D   166
  50    04 BC    00008000 8F      CB    001D   167 START:  BICL3   #^X8000, @DIVIDEND(AP), R0      ; R0 = |X|
                                0026   168
    54    52    FFFF007F 8F      CB    0026   169          BICL3   #^XFFFF007F, R2, R4             ; R4 = m the exponent of Y
    53    50    FFFF007F 8F      CB    002E   170          BICL3   #^XFFFF007F, R0, R3             ; R3 = n the exponent of X
                     53    54    C2    0036   171          SUBL2   R4, R3                          ; R3 = c = m-n
                                0039   172                                                        ; plus some low order bits
                        69    19    0039   173          BLSS    GET_SIGN                        ; If c<0 then |X| > |Y| and the
                                003B   174                                                        ;   result is X
                                003B   175 ;+
                                003B   176 ;
                                003B   177 ;       STEP_2
                                003B   178 ;       Extract the fraction part of X*2^24, called I, and the
                                003B   179 ;       fractional part of Y*2^24, called J.
                                003B   180 ;
                                003B   181 ;       After the exponent bits are removed from the internal F_floating
                                003B   182 ;       point representation, the hidden bit needs to be added into the
                                003B   183 ;       internal representation since the number is to be converted to
                                003B   184 ;       an integer value.
                                003B   185 ;
                                003B   186 ;-
                                003B   187
        50    7F80 8F      AA    003B   188          BICW    #^X7F80, R0                     ; Clear the exponent field
  50     00000080 8F      C0    0040   189          ADDL2   #^X80, R0                       ; Replace hidden bit
        50    50    10        9C    0047   190          ROTL    #16, R0, R0                     ; Convert to integer (R0 = I)
                                004B   191
        52    7F80 8F      AA    004B   192          BICW    #^X7F80, R2                     ; Clear the exponent field
  52     00000080 8F      C0    0050   193          ADDL2   #^X80, R2                       ; Replace hidden bit
        52    52    10        9C    0057   194          ROTL    #16, R2, R2                     ; Convert to integer (R2 = J)
                                005B   195
              52    50    D1    005B   196          CMPL    R0, R2                          ; Compare I and J
                     03    19    005E   197          BLSS    STEP_3                          ; Branch if I < J
              50    52    C2    0060   198          SUBL2   R2, R0                          ; I <-- I - J
                                0063   199
                                0063   200 ;+
                                0063   201 ;
                                0063   202 ;       STEP_3
                                0063   203 ;       Convert c = exponent of X - exponent of Y into an integer.
```

```
                                0063   204 ;       Subtract 31 from c in order to determine if an iteration
                                0063   205 ;       of the algorithm is needed. If c-31>=0 then go to STEP_5.
                                0063   206 ;
                                0063   207 ;-
                                0063   208
        53   53    F9 8F   9C  0063   209 STEP_3: ROTL    #-7, R3, R3                 ; Convert c to an integer value
                  53 1F   A2  0068   210         SUBW    #31, R3                     ; Check shift count, c = c-31
                     1A   19  006B   211         BLSS    STEP_5                      ; Branch, if c < 0
                                006D   212
                                006D   213 ;+
                                006D   214 ;
                                006D   215 ;       STEP_4
                                006D   216 ;       Compute I = L - J*int(2^c*I/J) by rem(2^c*I, J) since I and
                                006D   217 ;       J were scaled to integer values.
                                006D   218 ;
                                006D   219 ;-
                                006D   220
        51   50    FF 8F   9C  006D   221 STEP_4: ROTL    #-1, R0, R1                 ; R0/R1=2^31*I. This and the next
50      51   7FFFFFFF 8F   CB  0072   222         BICL3   #^X7FFFFFFF, R1, R0         ; two instructions are equivalent
                                007A   223                                             ; to ASHQ #31,R0,R0, but are faster
             51   50    C2  007A   224         SUBL2   R0, R1                      ; R0/R1 contains L = 2^31*I
     50      51   50    52  7B  007D   225         EDIV    R2, R0, R1, R0              ; R0 = rem(2^31*I,J)
             53   1F    A2  0082   226         SUBW2   #31, R3                     ; Check shift count, c = c-31
                  E6    18  0085   227         BGEQ    STEP_4                      ; Branch if c >=0
                                0087   228
             53   1F    A0  0087   229 STEP_5: ADDW2   #31, R3                     ; Restore shift count, c = c+31
                  0B    13  008A   230         BEQL    STEP_7                      ; If zero, branch to STEP_7
                                008C   231 ;+
                                008C   232 ;
                                008C   233 ;       STEP_6
                                008C   234 ;       Compute I = L - J*int(2^c*I/J) by rem(2^c*I, J) since I and
                                008C   235 ;       J were scaled to integer values.
                                008C   236 ;
                                008C   237 ;-
             51   D4    008C   238         CLRL    R1                          ;
        50   50   53    79  008E   239         ASHQ    R3, R0, R0                  ; R0 = 2^c*I
50      51   50   52    7B  0092   240         EDIV    R2, R0, R1, R0              ; R0 = rem(2^c*I, J)
                                0097   241
             50   50    4E  0097   242 STEP_7: CVTLF   R0, R0                      ; Convert I to floating point
        50   4C00 8F    A2  009A   243         SUBW2   #^X4C00, R0                 ; R0 = 2^(-24) * I
             50   54    A0  009F   244         ADDW2   R4, R0                      ; R0 = 2^(m-24) * I
                  09    19  00A2   245         BLSS    UNDERFLOW                   ; Branch if underflow occured
                                00A4   246 GET_SIGN:
                04 BC    B5  00A4   247         TSTW    @DIVIDEND(AP)               ; Check for sign of result
                  03    18  00A7   248         BGEQ    RETURN                      ;  and adjust answer accordingly
             50   50    52  00A9   249         MNEGF   R0, R0                      ;
                  04    04  00AC   250 RETURN: RET
                                00AD   251
                                00AD   252 UNDERFLOW:
             50   D4    00AD   253         CLRL    R0                          ; set up default result to 0.0
    0D 04 AD   06   E1  00AF   254         BBC     #SF$V_FU, SF$W_SAVE_PSW(FP), NO_FU
                                00B4   255                                             ; Branch if caller has not enabled F
      00000000'8F   DD  00B4   256         PUSHL   #MTH$K_FLOUNDMAT                    ; Report MTH$_FLOUNDMAT
00000000'GF   01    FB  00BA   257         CALLS   #1, G^MTH$$SIGNAL                   ; Signal the error
                  04    00C1   258 NO_FU:  RET                                 ; Return
                                00C2   259
                                00C2   260         .END
```

```
DIVIDEND        =  00000004
DIVISOR         =  00000008
GET_SIGN           000000A4  R      02
MTH$$SIGNAL        ********    X    00
MTH$AMOD           00000000  RG     02
MTH$K_FLOUNDMAT    ********    X    00
MTH$K_INVARGMAT    ********    X    00
NO_FU              000000C1  R      02
RETURN             000000AC  R      02
SF$V_FU         =  00000006
SF$W_SAVE_PSW   =  00000004
START              0000001D  R      02
STEP_3             00000063  R      02
STEP_4             0000006D  R      02
STEP_5             00000087  R      02
STEP_7             00000097  R      02
UNDERFLOW          000000AD  R      02
```

Psect synopsis

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
ABS	00000000 (0.)	01 (1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
_MTH$CODE	000000C2 (194.)	02 (2.)	PIC USR CON REL LCL SHR EXE RD NOWRT NOVEC LONG

Performance indicators

Phase	Page faults	CPU Time	Elapsed Time
Initialization	30	00:00:00.10	00:00:01.11
Command processing	122	00:00:00.50	00:00:03.31
Pass 1	115	00:00:01.17	00:00:05.46
Symbol table sort	0	00:00:00.02	00:00:00.05
Pass 2	56	00:00:00.60	00:00:03.58
Symbol table output	3	00:00:00.02	00:00:00.03
Psect synopsis output	2	00:00:00.03	00:00:00.05
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	330	00:00:02.44	00:00:13.59

```
The working set limit was 1050 pages.
5219 bytes (11 pages) of virtual memory were used to buffer the intermediate code.
There were 10 pages of symbol table space allocated to hold 44 non-local and 0 local symbols.
260 source lines were read in Pass 1, producing 13 object records in Pass 2.
8 pages of virtual memory were used to define 7 macros.
```

```
                    +----------------------------+
                    ! Macro library statistics !
                    +----------------------------+

Macro library name                    Macros defined
------------------                    --------------
_$255$DUA28:[SYSLIB]STARLET.MLB;2                4

88 GETS were required to define 4 macros.

There were no errors, warnings or information messages.

MACRO/ENABLE=SUPPRESSION/DISABLE=(GLOBAL,TRACEBACK)/LIS=LIS$:MTHAMOD/OBJ=OBJ$:MTHAMOD MSRC$:MTHAMOD/UPDATE=(ENH$:MTHAMOD)
```

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY